

Pattern Information

Date	30.9.2011
Pattern Type	Recreational
Pattern Difficulty	Low
Pattern Designer	

Surface Information

Surface Type	Synthetic
Surface Brand	Brunswick Anvil Lane
Age	3

Pattern Parameters

Pattern Number	1
Pattern Name	EZ 1.0
Mode	Clean & Oil
Forward Speed	Max Clean/Reduced
Start Cleaner Spray	0
Start Squeegee	0
Start Oiling	6
Split Pattern	No

Supplies Information


Lane Cleaner	Brunswick AW22
Cleaner Mixture Ratio	4 : 1
Cleaner Transition Distance	53
Lane Conditioner	Brunswick AW22

Notes

Slovak Bowling Federation

Zone	1	2	3	4	5	6	7	8
Zone End Distance	10	18	25	31	42			
Zone Ratio	L 3,8 : 1 R 3,8 : 1	5,0 : 1 5,0 : 1	7,8 : 1 7,8 : 1	9,0 : 1 9,0 : 1	### : 1 ### : 1	### : 1 ### : 1	### : 1 ### : 1	### : 1 ### : 1

ZONE	7 Pin Side												Board Number												10 Pin Side																
	L1	L2	L3	L4	L5	L6	L7	L8	L9	L10	L11	L12	L13	L14	L15	L16	L17	L18	L19	C20	R19	R18	R17	R16	R15	R14	R13	R12	R11	R10	R9	R8	R7	R6	R5	R4	R3	R2	R1		
1	25	25	25	25	25	25	25	25	27	45	60	75	75	75	90	95	95	95	95	95	95	95	95	95	95	75	75	75	60	45	27	25	25	25	25	25	25	25	25	25	
2	15	15	15	15	15	15	15	15	15	17	40	60	65	65	75	75	75	75	75	75	75	75	75	75	75	65	65	60	40	17	15	15	15	15	15	15	15	15	15	15	
3	7	7	7	7	7	7	7	7	7	7	9	40	50	50	55	55	55	55	55	55	55	55	55	55	55	50	50	40	9	7	7	7	7	7	7	7	7	7	7	7	
4	5	5	5	5	5	5	5	5	5	5	7	25	40	40	45	45	45	45	45	45	45	45	45	45	45	40	40	25	7	5	5	5	5	5	5	5	5	5	5	5	
5	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
6																																									
7																																									
8																																									



AUTHORITY 22®

Crosswise Ratios

	Zone 1	Average	Ratio
3L-7L	Left =	25,0	3,8
3R-7R	Right=	25,0	3,8
18L-18R	Center =	95,0	

	Zone 2	Average	Ratio
3L-7L	Left =	15,0	5,0
3R-7R	Right=	15,0	5,0
18L-18R	Center=	75,0	

	Zone 3	Average	Ratio
3L-7L	Left =	7,0	7,8
3R-7R	Right=	7,0	7,8
18L-18R	Center=	55,0	

	Zone 4	Average	Ratio
3L-7L	Left =	5,0	9,0
3R-7R	Right=	5,0	9,0
18L-18R	Center =	45,0	

	Zone 5	Average	Ratio
3L-7L	Left =	0,0	#####
3R-7R	Right=	0,0	#####
18L-18R	Center=	0,0	

	Zone 6	Average	Ratio
3L-7L	Left =	#####	#####
3R-7R	Right=	#####	#####
18L-18R	Center=	#####	

	Zone 7	Average	Ratio
3L-7L	Left =	#####	#####
3R-7R	Right=	#####	#####
18L-18R	Center =	#####	

	Zone 8	Average	Ratio
3L-7L	Left =	#####	#####
3R-7R	Right=	#####	#####
18L-18R	Center=	#####	

The crosswise ratios are calculated by the average units of oil for boards 18L - 18R and divided by the average units of oil for board 3 - 7 left and right.

Brunswick®

AUTHORITY22®

	3L-7L	18L-18R	3R-7R
	Left	Center	Right
Zone 2	1,6	1,2	1,6
Zone 3	3,5	1,7	3,5
Zone 4	5,0	2,1	5,0
Zone 5	#####	#####	#####
Zone 6	#####	#####	#####
Zone 7	#####	#####	#####
Zone 8	#####	#####	#####

[illegible]

The lengthwise ratios are calculated from the volumes in the first zone.